	Prir	mary Drinking	water S	<u>standards</u>				<u> Prinking v</u>	<u> Water Standards</u>
						(CONTINUED)			
	Maximum Contaminant	Maximum Contaminant				Maximum Contaminant	Maximum Contaminant		
	Level Goal	Level	Actual			Level Goal	Level	Actual	
rameter	MCLG	MCL	Test Results	Likely Source:	Parameter	MCLG	MCL	Test Results	Likely Source:
arity rbidity (ntu) (12) (TT)					Organic Chemicals (continued) Tetrachloroethylene (PCE) (ppb)		F		Discharge from factories and dry cleaners.
rolalty (ntu) (12) (11)	n/a	5.0		Soil runoff.	Toluene (ppm)	1	5		Discharge from petroleum factories.
crobiological					Total Trihalomethanes (TTHMs) (8) (ppb)	0	80		By-product of drinking water chlorination.
otal Coliform bacteria (<40 samples)	0	1		Naturally present in the environment.	Toxaphene (ppb)	0	3		Runoff/leaching from insecticide used on cotton and cattle.
% of samples positive (>40 samples	0	5.0		reactivity present in the cirvitoninent.	Trichlorobenzene (1,2,4-) (ppb)	70	70		Discharge from textile finishing factories
					Trichloroethane (1,1,1-) (TCA) (ppb)	200	200		Discharge from metal degreasing sites and other factories.
ganic Chemicals 4-D (ppb)					Trichloroethane (1,1,2-) (ppb)	3	5		Discharge from industrial chemical factories.
I-D (ppb)	70 400	70		Runoff from agricultural herbicide.	Trichloroethylene (TCE) (ppb)	0	5		Discharge from metal degreasing sites and other factories.
ipate (diethylhexyl) (ppb achlor (ppb)	400	400		Runoff from agricultural herbicide. Runoff from agricultural herbicide.	Vinyl Chloride (ppb) Xylenes (ppm)	10	10		Leaching from PVC piping. Discharge from plastic factories.  Discharge from petroleum factories. Discharge from chemical factories.
licarb (ppb)	1	3		Runoff from agricultural herbicide.	Aylenes (ppin)	10	10		Discharge from perfordin metorics. Discharge from chemical factories.
dicarb Sulfone (ppb)	1	3		Runoff from agricultural herbicide.	Inorganic Chemicals				
licarb Sulfoxide (ppb)	1	3		Runoff from agricultural herbicide.	Antimony (ppb)	0	6		Discharge from petroleum refineries, fire retardants, ceramics, electronics, and solder.  Erosion of natural deposits. Runoff from orchards, glass and electronics production wastes.
azine (ppb)	3	3		Runoff from agricultural herbicide.  Discharge from factories, gasoline storage tanks, and landfills.	Arsenic (ppb) (15)	0	10		Erosion of natural deposits. Runoff from orchards, glass and electronics production wastes.  Decay of asbestos cement water mains. Erosion of natural deposits.
nzene (ppb) nzo (a) Pyrene (2) (ppt)	0	200		Leaching from linings of water storage tanks, and distribution lines	Asbestos (1) (MFL) Barium (ppm)	2	7		Discharge of drilling wastes. Discharge from metal refineries. Erosion of natural deposits.
mate (ppb)	0	10		By-product of drinking water chlorination.	Bervllium (pph)	4	4		Discharge from metal refineries, coal burning factories, electrical, aerospace and defense industries.
bofuran (ppb)	40	40		Leaching of soil fumigant used on rice and alfalfa.	Cadmium (ppb)	5	5		Discharge from metal refineries, galvanized pines, waste batteries and paints. Erosion of natural deposit
rbon Tetrachloride (ppb)	0	5		Discharge from chemical plants and other industrial activities.	Chromium (Total) (ppb)	100	100		Discharge from steel and pulp mills. Erosion of natural deposits.  Corrosion of household plumbing systems.  Discharge from steel/melt factories. Discharge from plastic and fertilizer factories.
ordane (ppb)	0	2		Residue of banned termiticide.  Water additive used to control microbes.	Copper (7) (ppm) [] sites failed out of [] sampled	AL = 1.3 200	AL = 1.3 200		Corrosion of household plumbing systems.
loramines (ppm) lorobenzene (ppb)	100	100	+	Water additive used to control microbes.  Discharge from chemical and agricultural factories.	Cyanide(ppb) Fluoride (6) (ppm)	200	200	-	Erosion of natural deposits. Water additive which promotes strong teeth.
lorine (ppm)	4	4	1	Water additive used to control microbes.	Lead (7) (ppb) [] sites failed out of [] samplec	0	AL = 15		Corrosion of household plumbing systems
lorite (ppm)	0.8	i		Water additive used to control microbes.	Mercury (ppb)	2	2		Historian of natural denocity. Discharge from refineries and factories, landfills
lorine Dioxide (ppb)	800	800		Water additive used to control microbes.	Nitrate (ppm)	10	10		Runoff from fertilizer use. Leaching from septic tanks, sewage. Erosion of natural deposits.  Runoff from fertilizer use. Leaching from septic tanks, sewage. Erosion of natural deposits.
lapon (ppb)	200	200		Runoff from herbicides used on rights-of-way.	Nitrite (ppm)	1	1		Runoff from fertilizer use. Leaching from septic tanks, sewage. Erosion of natural deposits.
(2-ethylhexyl) adipate (ppb (2-ethylhexyl) phthalate (PAE) (ppb	0	400	1	Discharge from chemical factories.  Discharge from rubber and chemical factories.	Selenium (ppb) Thallium (ppb)	50	50		Discharge from petroleum and metal refineries. Erosion from natural deposits. Discharge from mines. Leaching from ore processing sites. Discharge from electronics, glass and drug factories.
promochloropropane (DBCP) (2) (ppt)	0	200		Soil fumigant used on soybeans, cotton, pineapples, and orchards.	mailium (ppo)	0.5	2		Leaching from ore processing sites. Discharge from electronics, glass and drug factories.
chlorobenzene (p-) (ppb)	75	75		Discharge from industrial chemical factories.					
hlorobenzene o- (Ortho-) (ppb)	600	600		Discharge from industrial chemical factories					
hloroethane (1,2-) (ppb)	0	5		Discharge from industrial chemical factories.					
hloroethylene (1,1-) (ppb)	7	7		Discharge from industrial chemical factories.					
hloroethylene (Cis-1,2-) (ppb)	70	70	-	Discharge from industrial chemical factories.					
hloroethylene (Trans-1,2-) (ppb) hloromethane (ppb)	100	100	-	Discharge from industrial chemical factories.  Discharge from pharmaceutical and chemical factories.	Radionuclides Gross Alpha Activity (9) (pCi/l		45		Naturally occurs in some drinking water sources.
chloropropane (1,2-) (ppb)	0	5		Discharge from industrial chemical factories.	Radium 226/228 (Combined) (pCi/l)	0	5		Naturally occurs in some drinking water sources.
noseb (ppb)	7	7		Runoff from herbicide used on soybeans and vegetables.	Uranium (10) (ug/l)	0	30		Naturally occurs in some drinking water sources.
oxin (3) (ppq)	0	30		Emissions from waste incineration, and discharge from chemical factories.	Radon (16) (pCi/l)	300	4,000		Naturally occurs in some drinking water sources.
quat (4) (ppb)	20	20		Runoff from herbicide use.					
dothall (4) (ppb)	100	100		Runoff from herbicide use. Residue of banned insecticide.	Other Cryptosporidium/Giardia (11)	0	^		Naturally occurs in some drinking water sources.
hylbenzene (ppb)	700	700		Discharge from petroleum refineries.	Cryptosporidium/Giardia (11)	0	U		Naturally occurs in some drinking water sources.
				9 1				<del></del>	
hylene Dibromide (EDB) (5) (ppt)	0	50		Discharge from petroleum refineries.		Secondary Drin	iking Water Sta	<u>indards</u>	
yphosate (3) (ppb)	700	700		Runoff from herbicide use.	Chemical Parameters				
loacetic Acids (ppb)	0	60 400		Disinfection byproduct.  Residue of banned termiticide.	Chlorida (nam)	250	250		Naturally occurs in some drinking water sources.
ptachlor (ppt) ptachlor Epoxide (ppt)	0	200		Breakdown of Heptachlor.	Chloride (ppm) Iron (ppb)	250 300	250 300		Naturally occurs in some drinking water sources.
ptachlor/Heptachlor Epoxide (ppt)	0	200		Discharge from metal refineries and agricultural chemical factories.	Manganese (ppb)	50	50		Naturally occurs in some drinking water sources.
xachlorobenzene (ppb)	0	1	1	Discharge from chemical factories.	Silver (ppb)	100	100		Naturally occurs in some drinking water sources.
xachlorocyclopentadiene (ppb)	50	50		Discharge from chemical factories.	Sodium (ppm)	100	100		Naturally occurs in some drinking water sources.
dane (ppt)	200 40	200 40		Runoff/leaching from insecticide used on cattle, lumber, gardens. Runoff/leaching from insecticide used on fruits, vegetables, and livestock.	Sulfate (ppm)	250 500	250 500		Naturally occurs in some drinking water sources.
thoxychlor (ppb) thyl-Tertiary-Butyl-Ether (MTBE) (13) (ppb		40	1	Reformulated gasoline additive.	Total Dissolved Solids (ppm) Zinc (ppm)	500	500		Naturally occurs in some drinking water sources.  Naturally occurs in some drinking water sources.
amyl (Vydate) (ppb)	35 200	200	1	Runoff/leaching from insecticide used on apples, potatoes and tomatoes.	спо (ррпі)	3	5		raman, ocean in some drinking water sources.
ntachlorophenol (ppb)	0	1		Discharge from wood preserving factories.					
loram (ppb)	500	500		Herbicide runoff.	Physical Parameters				
ychlorinated Biphenyls (PCBs) (ppt	50	500		Runoff from landfills. Discharge of waste chemicals.	Color (units)	15.0 6.5-8.5	15.0 6.5-8.5		
vex (2,4,5-TP) (ppb) mazine (ppb)	50	50	+	Residue of banned herbicide. Herbicide runoff	рн	6.5-8.5	6.5-8.5	-	
rene (ppb)	100	100	1	Discharge from rubber and plastic factories. Leaching from landfills.	Footnotes:	+			
· · · vrF=/	100				(1) Asbestos: State wide waiver to testing in Maine. C	only those systems with asbestos	pipe need tes		
finitions:					(2) Dibiomocnioroproparie. State wide waiver granted	I to maine			
kimum Contaminant Level Goal (MCLG) establ	lished by EPA The level of a con	taminant in drinking water be	low which there is	no known or expected risk to health	(3) Dioxin/Glyphosate: State wide waiver granted to N	/aine			
s is not the acceptable regulatory compliance li ximum Contaminant Level (MCL): The highest	level of a contaminant that is all	owed in the drinking water.	hie ie ueod to date	ermine compliant	(4) Diquat/Endothall: Testing only required if potato g (5) Ethylene Dibromide: Testing only required for ground for grou	rowing occurs in watershed	niver for curfees water	ome in Mein	
kimum Contaminant Level (MCL): The nignest kimum Residual Disinfectant Level Goal (MRD	I G):The level of a drinking water	disinfectant below which the	e is no known or e	expected risk to health	(6) Fluoride: Fluoride levels must be maintained betw	und water systems. State wide w	aiver for surface water systems that fluoridate the wat	te III IVIdIN	
DLGs do not reflect the benefits of the use of o	disinfectants to control microbial	contaminants			(7) Lead/Copper: Action levels are measured at cons	sumer's tap. 90% of the tests mi	ist be equal to or below the	action leve	
imum Residual Disinfectant Level (MRDL: The	e highest level of a disinfectant a	llowed in drinking water			(8) Total Trihalomethanes: Sum of Bromodichloromet	hane, Bromoform, Chlorodibrom	omethane		
re is convincing evidence that addition of a dis	sinfectant is necessary for control	of microbial contaminant:			and Chloroform, can not exceed 80 ppb.				
riance of Waiver: State or U.S. EPA permission	n not to meet MCL or treatment to	echnique under certain condi	ions (e.g. waiver t	to filtration	(9) Gross Alpha: Action level over 5pCi/l requires test	ing for Radium. Action level over	15pCi/I requires testing for	Uranium and Rado	dead to December 2000
eatment Technique (TT): A required process intition Level (AL): The concentration of a contami	inant which, if exceeded, tricage	intaminant in drinking water (	e.g. turbidity	system must follow (e.g. lead, connei	(10) Uranium: The U.S. EPA adopted the new MCL s (11) Cryptosporidium, Giardia, Legionella - Surface W	tandard of 30 ppb, in December	ZUUU. Water systems must	meet this new stan	dara by December 2003
			minori a water	cyclom maccionow (c.g. icau, copper	(11) Cryptosporidium, Giardia, Legionella - Surface vi (12) Turbidity: Surface waters only; 1.49 ntu for Slow	Sand or AFT, 0,549 ntu for Conv	entional or Direct Filtration	5.0 ntu for unfiltere	I d surface/ground water system:
ncentrations: In this report, most of the quant	tities are expressed as ppm, ppb	p, ppt and pCi/		<del> </del>	Turbidity (continued): Surface water supplies mu	ist meet the treatment technique	level in 95% of the samples	s take	yy
se are measure of organics, inorganics or radi	iation activity per a fixed amount	of wate			(13) MTBE: State of Maine MCL standard of 35 ppb v	vas adopted in February 1998.			
ts per Million (ppm). Is the equivalent of one di	rop of chemical per every 10 gall	ons			(14) MFL: Million Fibers per Liter				
ts per Billion (ppb): Is the equivalent of one dro	op of chemical per every 10,000	gallons			(15) Arsenic: The U.S. EPA adopted the new MCL st	andard of 10 ppb, in October 20	01. Water systems must me	eet this new standa	rd by January 2006
rts per Trillion (ppt) Is the equivalent of one dro ocurries per Liter (pCi/I) Is a measure of the au	op of chemical per every 10,000,000 or chemical per every 10,000 or che	tion per liter of wate	+		(16) Radon: The U.S. EPA is proposing setting lower The State of Maine currently recommends treatment	standards for public drinking wa	ter between 300-4,000 pCi/	L	
phelometric Turbidity Units (ntu): Turbidity Unit	are the management of clauding	non per mer or water	+		The state of maine currently recommends treatment	ioi radonieveis ili dilliking Wate	above 20,000 poi/L	+	
phelometric Turbidity Units Intil: Turbidity Unit									